
Last Updated: October, 2019 Version: ArcMap 10.X

EXERCISE 1 Access the Services



Introduction

Image services and the RDW are GIS Services that allows users to efficiently access and display large volumes of raster data from a central server. You can enjoy easy access to current high resolution imagery such as NAIP without the hassle of storing so much data.

Objectives

Learn how to connect to Image Services and the RDW within ArcGIS and outside of it.

Table of Contents

Part 1: Access the Services in ArcMap	. 2
·	
Part 2: Access the Services on REST pages	
Part 3: Access the Services in AGOL	. 6



Part 1: Access the Services in ArcMap


You can connect to Image Services and the RDW in ArcMap using either the Catalog or Add Data button.

A. Connect using Catalog

- 1. Launch ArcMap from the start menu by clicking Start | Programs | ArcGIS | ArcMap.
- 2. Close any start-up screens that may appear.
- 3. From within ArcMap, if needed activate Catalog by either clicking on **Windows | Catalog** or by clicking on the Catalog icon in the main toolbar (see below).



- i. Dock the toolbar if desired.
- 4. Find the GIS Servers item, and click the plus sign next to it to expand the list.
- 5. Double-click on **Add ArcGIS Server** (see below).



- 6. In the box next to Server URL:, type in one of the following addresses:
 - i. Image Services: https://image-services-gtac.fs.usda.gov/arcgis/services
 - ii. Internal RDW Map: https://apps.fs.usda.gov/arcn/services
 - iii. Internal RDW Raster: https://apps.fs.usda.gov/fsgisn01/services
 - iv. External RDW Map: https://apps.fs.usda.gov/arcx/services
 - v. External RDW Raster: https://apps.fs.usda.gov/fsgisx01/services



ArcGIS Server User Connection Properties		
General		
Server URL:	>s://image-services-gtac.fs.usda.gov/arcgis/rest/services ArcGIS Server: http://gisserver.domain.com:6080/arcgis	

- 7. Leave the User Name and Password boxes blank, and click **Finish** (see above).
- 8. The service will be added to the list under GIS Servers.
- 9. Expand the lists by clicking on the plus signs to see the available data (see below).



10. To add a service to your map, simply click-and-drag the service to your map window or Table of Contents.


B. Connect Using Add Data in ArcMap

- 1. Click on the **Add Data** button, or right-click on **Layers** in the Table of Contents and choose **Add Data**.
- 2. Next to **Look in**, click on the drop down and select **GIS Servers** (see below).






3. In the list, double-click on Add ArcGIS Server (see below).



- 4. Ensure that **Use GIS Services** is selected, and click on **Next** >.
- 5. In the box next to **Server URL**, enter one of the addresses listed in section A, step 6.
- 6. Leave the User Name and Password boxes blank, and click **Finish**.
- 7. The server https://image-services-gtac.fs.usda.gov/arcgis/services will be added to the list. Double click on it.
- 8. The list of services will now appear in the Add Data dialog (see below.) To see what is available in a folder, double-click it. To move up a level, click on the **Up One Level** tool to the right of the Look in drop down.



- 9. To add the desired service, click on it then click on **Add**.
 - The server will now be available below GIS Servers in the Look in drop down until you remove it.



Part 2: Access the Services on REST pages

You can access the Image Services and RDW data on their REST pages. REST is an acronym for Representational State Transfer which is a method of transferring information to your web browser. On the server REST pages you will find descriptions and metadata for each of the services.


- 1. Visit one of the following REST pages:
 - i. Image Services: https://image-services-gtac.fs.usda.gov/arcgis
 - ii. External RDW: https://apps.fs.usda.gov/arcx/rest/services
 - iii. Internal RDW: https://apps.fs.usda.gov/arcn/rest/services
- 2. On the page, click one of the folders then click one of the services.
 - i. You can navigate up levels using the breadcrumbs near the top of the page, or by using your browser's Back button.
- 3. You should now see a page with several options for viewing the service and a description of it.



- 4. Click the **Google Earth** option for viewing the service. You should now see a .kmz file has been downloaded.
- 5. If you don't already have Google Earth installed, please visit the Google Earth install page.
- 6. Open Google Earth and load the kmz file.
- 7. In the **Places** window, click on the file to zoom the viewer to the image layer (see following graphic).







There is now an Early Access Web Service (EAWS) which is an ESRI Restful 4 band image service that contains pre-production NAIP imagery. The imagery is added to the service, on average, 5 business days after the imagery acquisition. This imagery is minimally processed to speed up the posting of imagery to the image service. For more information, refer to this document.

Part 3: Access the Services in AGOL

ArcGIS Online (AGOL) is a cloud based Web GIS content management platform for collaboration and sharing of maps, applications, data and other geospatial information. The Forest Service is implementing AGOL enterprise wide to provide a method for publishing and communicating both standard and non-standard, unit-level spatial information to the public, agency cooperators, and other government entities.

- 1. You must first setup an AGOL account by visiting this site: https://apps.fs.usda.gov/gtactools/AGOL/request access.php
 - i. After you have submitted the application, you should receive an email from an FS AGOL administrator with directions to setup your password.
- 2. Visit the FS AGOL website: usfs.maps.arcgis.com.

The AGOL site often doesn't work well in Chrome so it's best to use a different browser.

3. Click the **Sign In** button in the upper right corner of the page (outlined in red below).








4. Click the **Map** button on the main menu (outlined in red below).



5. On the top menu bar, click Add | Search for Layers (see below).




- 6. In the Search for Layers window, set the In: field to "A GIS server".
- 7. In the URL field, enter one of the following REST URLs:
 - i. Image Services: https://image-services-gtac.fs.usda.gov/arcgis/rest/services
 - ii. RDW Internal Services: https://apps.fs.fed.us/arcn/rest/services
 - iii. RDW External Services: https://apps.fs.fed.us/arcx/rest/services

Important: The URLs must start with https, not http.







8. Add one of the service layers to the map by click the **Add** button to the right of its name (see above).

